
Software Release Notes

Christie 4K7-HS/4K10-HS version 1.3.0

This document describes the changes from Christie 4K7-HS/4K10-HS version 1.2.0 to version 1.3.0.



If your projector has a firmware version older than version 1.2.0, after upgrading the firmware, perform both a factory and network reset. For information regarding the reset, contact Christie Technical Support.

Affected products

The following products are affected:

- Christie 4K7-HS
- Christie 4K10-HS

Purpose of release

The primary purpose of this software release is:

- Added the UART command for the Dynamic black function.
- Added the Auto test pattern to the web user interface.
- Improved 3D functionality.
- Improved the power on/off sequence.
- Fixed the lens function commands.
- Improved Christie Twist and Mystique functionality.
- Fixed a color space issue.
- Added compliance for California Civil Code Section 1798.91.04.
- Addressed an image issue when switching between 2D and 3D.
- Provided minor fixes and improvements over version 1.2.0.

Known issues

This release of Christie 4K7-HS/4K10-HS contains the following known issues.

- When using an existing configuration on Christie Twist/Mystique and you are prompted to clear the test patterns, the projector may clear the test pattern regardless of the given response.
- If Christie Twist, Mystique, or an external software script is used to power on the projector at the same time, the projector may remain in a warming up state.

Workaround: AC power cycle the projector and only power it on from a single application, side panel controls, or IR remote.

Technical support

- North and South America: +1-800-221-8025 or *Support.Americas@christiedigital.com*
- Europe, Middle East, and Africa: +44 (0) 1189 778111 or *Support.EMEA@christiedigital.com*
- Asia Pacific: +65 6877-8737 or *Support.APAC@christiedigital.com*