

---

# Software Release Notes

---

## Mystique version 2.13.1

This document provides the changes from Mystique version 2.13 to 2.13.1.

### Purpose of release

The following fixes are included in this release.

- Provided fixes over version 2.13.  
For details, see the CHANGELOG.md file located in C:\Program Files\Christie Digital Systems\Mystique 2.13\docs\CHANGELOG.md.

### Known issues

The following are known issues in this release.

- If a camera is disconnected while Mystique is open, the preview may become unavailable even after it has been reconnected.  
*Resolution:* If this happens, launch the camera search or reload the configuration to restore camera functionality.
- The performance of Mystique with FLIR cameras in the configuration seems slow (or slower than before installing the Dalsa drivers). Occasionally, the Status Viewer shows warnings indicating the camera could not retrieve an image.  
*Resolution:* Disable Dalsa drivers. For more details, see the "Point Grey or FLIR camera performance is slow" topic in the *Mystique User Guide (P/N: 020-001134-XX)*
- Installing or uninstalling combinations of Christie software products including Mystique, AutoCal, AutoStack, Conductor on the same computer may cause communication issues with cameras or projectors on some of the products.  
*Workaround:* To restore all drivers and dependencies, remove then re-install the latest version of Mystique.
- When using an existing configuration on Mystique and you are prompted to clear the test patterns, HS Series, GS Series, and Inspire Series projectors may clear the test pattern regardless of the given response.
- Drawing test patterns using Mystique Operate is not supported on the Christie HS Series, GS Series, Inspire Series, Jazz Series, and Korus Series projectors.
- Christie Twist™ files generated by Christie Mystique containing Christie Pandoras Box projectors cannot be opened by Twist.
- In some cases, it may take up to 10 seconds to add Ethernet cameras in Christie Mystique.
- If an installation includes a completely flat screen, or a projector with a mirrored X or Y axis, the installation cannot be supported by a fish eye fit solver.
- If connected to Pandoras Box® and using multiple Pandoras Box Sites, inconsistencies may occur with the canvases in the Mystique integration folder in Pandoras Box, and cause Mystique

to create new canvases. The unused inconsistent canvases remain in the Pandoras Box project and saved to disk, and may cause a buildup of unused canvases.

*Workaround:* Delete the unused canvases from the Pandoras Box project or from disk. To prevent canvases from becoming inconsistent in the future, in Pandoras Box, select the **Inspector** tab. In the File Management area, remove any canvases from untargeted nodes displaying an inconsistent status.

- Computers with an Intel HD Graphics 530 and certain versions of its driver may cause Mystique to crash while launching.  
*Workaround:* Install graphics driver version 21.20.16.4627, which has been tested and is compatible with Mystique.
- On some computers, running a Mystique 3D configuration from Mystique Operate may report an Abnormal Error preventing the Run from completing successfully.  
*Workaround:* In Mystique, disable drawing test patterns as part of the Run process. Save the change, close Mystique, and initiate the Run from Operate again.
- When connected to Pandoras Box, Mystique runs may fail if output parameters are overridden by running sequences.  
*Workaround:* Save the warp, soft-edge (blend), and source parameters of PB outputs to sequences not used to run the Pandoras Box show.
- Some Logitech C920 webcams stop working correctly after their initial use with Mystique. When relaunching Mystique, the camera is discoverable but if added to the configuration, no preview image is shown and the calibration fails.  
*Workaround:* Disconnect the webcam in between uses of Mystique.
- If Mystique cannot communicate with a remote Pandoras Box Manager, try disabling the firewall on the Pandoras Box computer.
- There are known instances of not being able to draw the 3D test pattern using Mystique Operate on some systems.  
*Workaround:* To see the 3D test pattern, open the calibration file in Mystique and select **Draw 3D Test Pattern**.

## Ensuring port 80 is not in use

Verify no other programs are using port 80 before installing Mystique.

There are two known services that might use port 80—the World Wide Web Publishing Service, and the Web Deployment Agent Service. If either service is running on your system, stop the service and change the startup type of the service to Manual before you install Mystique.

1. On your computer, select **Start > Control Panel > Administrative Tools > Services**.
2. Locate the **World Wide Web Publishing Service**.
3. Right-click the service and select **Properties**.
4. In the Startup type list, select **Manual**.
5. In the Service status area, select **Stop**.
6. Select **Apply**.
7. Repeat steps 2 to 6 for the **Web Deployment Agent Service**.

## Installing Mystique

To load Mystique, complete the following steps.

If a restart prompt appears before the installation is complete, select **No**.

1. Make sure all operating system patches are installed.
2. If an existing AutoCal or Mystique installation exists on the computer, Christie recommends uninstalling the application prior to loading the latest version of Mystique, unless the older installation is required for compatibility with older hardware.  
If an existing AutoCal or Mystique installation is uninstalled after loading the latest version of Mystique, Mystique may need to be removed and re-installed to correctly restore all drivers and dependencies.
3. Insert the Christie installation media in to the USB drive on the computer.  
If the installation does not start automatically, select **Start > Computer**. Browse to the Mystique installation media, and double-click the **MystiqueSetup.msi** file that corresponds to the installed version of Windows.
4. Select **Next**.
5. To proceed with the Mystique installation, select **Next**.
6. Select **I accept the terms in the License Agreement** and select **Next**.
7. Select **Install**.
8. Select **Finish**.  
The Mystique installation is complete.
9. When the installation is complete, restart the computer.

## Technical support

Technical support for Christie Enterprise products is available at:

- North and South America: +1-800-221-8025 or [Support.Americas@christiedigital.com](mailto:Support.Americas@christiedigital.com)
- Europe, Middle East, and Africa: +44 (0) 1189 778111 or [Support.EMEA@christiedigital.com](mailto:Support.EMEA@christiedigital.com)
- Asia Pacific ([support.apac@christiedigital.com](mailto:support.apac@christiedigital.com)):
  - China: +86 10 6561 0240 or [tech-supportChina@christiedigital.com](mailto:tech-supportChina@christiedigital.com)
  - India: +91 (80) 6708 9999 or [tech-India@christiedigital.com](mailto:tech-India@christiedigital.com)
  - Japan: 81-3-3599-7481
  - Singapore: +65 6877-8737 or [tech-Singapore@christiedigital.com](mailto:tech-Singapore@christiedigital.com)
  - South Korea: +82 2 702 1601 or [tech-Korea@christiedigital.com](mailto:tech-Korea@christiedigital.com)