
Technical Bulletin

Upgrading to CineLife+ software package 2.9.0

This bulletin provides information about upgrading your projector to CineLife+™ version 2.9.0 or higher (once released).

This upgrade contains updates and features provided in the software release notes. Make sure to read the software release notes prior to performing this upgrade. Christie recommends using this new software package.

The following outlines two notable updates:

- Diffuser Not Spinning critical alarm—The revolutions per minute (RPM) is measured every two seconds. If the RPM falls below 3000 RPM, a Diffuser Not Spinning critical alarm displays and the light source turns off.
- Light On (Exercise DMD) macro—A default Light On (Exercise DMD) macro provides the ability to automate the performance of the Enhanced Exercise DMD process.

Some additional improvements or features in the CineLife+™ 2.9.0 upgrade include the following:

- Increased the maximum channel name length from 35 to 50 characters.
- Added the ability to play back a playlist directly from the Playlist Editor menu.
- Improved the light source upgrade process to display progress as a percentage.
- Added the date and time to the Interrogator filename when an Interrogator is run from the web user interface.

Affected products

The following products are affected.

- All Series 4 Cinema projectors

Technical support

Technical support for Christie Cinema products is available at:

- Support.cinema@christiedigital.com
- +1-877-334-4267